

### Level 2 Certificate: Infection Prevention and Control (IPC) Lead <u>Module 3</u>

Presented by Chelsea Foster RDN.

### Module 3 Aim

For students to gain knowledge and understanding in preventing cross-infection.

### **Module 3 Objectives**

By the end of the module, students will be able to:

- State why preventing cross-infection is important.
- Demonstrate excellent understanding of hand hygiene.
- List facilities required in the dental practice. (continued)



IPC Lead Module 3 Slides Page 1 of 12

### **Module 3 Objectives (continued)**

- Describe why general hygiene is important and how to maintain this.
- Explain the correct procedure to disinfect impressions.
- State what PPE should be used and how to apply and remove this
- Describe how to decontaminate treatment areas.



### Importance of Cross Infection Control

### **Hand Hygiene**

### Hand Hygiene:

- Washing hands
- Disinfecting hands with rubs/gels

### Levels:

- Social/Routine
- Antiseptic
- Surgical



IPC Lead Module 3 Slides Page 2 of 12

### When To Complete Hand Hygiene


- Before and after each treatment session
- before and after removal of ppe
- After washing instruments
- Before contact with sterilized instruments regardless if they are wrapped
- After cleaning/maintaining the ultrasonic bath/washer disinfector/sterilizer etc
- At the end of decontamination



### **Hand Hygiene Policy**

- Between patients, before putting on gloves and after removal
- Do NOT use Bar soap, scrub or nail brushes
- Clean short nails, no false nails or varnish
- Clean nails with a blunt orange stick
- Dry with quality paper towels and techniques don't damage the skin
- Use of hand cream
- Alcohol rub visibly clean hands
- Foot/sensor operated bin





IPC Lead Module 3 Slides Page 3 of 12

## Surgical Scrub Technique Remove jewelry Wash with antimicrobial soap Time your handwash between 3-5 minutes If your hands touch anything add 1 minute for each section

### **Hand Hygiene Required Facilities**

All surgeries should be fitted with a separate hand washing basin on the clean side that is not used for cleaning instruments. This should have:

- No plug or overflow
- A sensor-operated or lever operated mixer tap
- Wall mounted Soap , Disinfectant and Cream dispensers with disposable cartridges
- 6 or 8 method Hand Hygiene poster above basin



### Skin Care

- Use of Hand Cream
- Short, clean fingernails no longer than the tip of your finger from palm view
- No nail varnish or false nails
- Bare from the elbow down, apart from a wedding band



IPC Lead Module 3 Slides Page 4 of 12

# General Hygiene Clean and presentable High level of personal hygiene Clean set of uniform each day

### **Disinfection of Impressions**

### Alginate:

• Rinse, dip, rinse, dip, wrap for 10 minutes and rinse

### Provil:

Soak for 10 minutes and rinse

### **Disinfection of Impressions**


### On return

- Disinfect for 10 minutes
- Check the correct solution for appliances with your local lab



IPC Lead Module 3 Slides Page 5 of 12

			Sending out	S				Chi Ret	barra	
Log Number	Patient ID	Dentist	Impression	Disinfected By	Disinfected	tah	Disinfected By	Disinfected	Stored	Audite
01	2094673	Dr Anderson	Alginate for MG	Cheisea	27,10.18	Knight	Chelsea	10.11.18	Labroom	Natalie IPC lead 01.12.18



### Protect hands Single use Powder free Nitrile or Vinyl should be used Latex can cause skin reactions

IPC Lead Module 3 Slides Page 6 of 12

### Used during decontamination process Washed with detergent and left to dry after use Replaced weekly or more frequently if damaged

### **Aprons**

- Worn during disinfection procedures
- Single use

### **Face and Eye Protection**

- Masks are single use
- Clean visors when visibly dirty or at the end of each clinical costion.
- Spectacles are not enough protection



IPC Lead Module 3 Slides Page 7 of 12

### **Footwear** Fully enclosed Good working order Comply with health and safety

### **Clinical Clothing**

- Changed daily
- Not to be worn outside
- Changing and storage facilities to be seperate to decontamination area



IPC Lead Module 3 Slides Page 8 of 12

### **PPE Removal**

 ${\ensuremath{\mathsf{Gloves}}}$  - Wash hands thoroughly if contaminated before removing the rest.

Apron - Break neck straps, gather apron together, and remove by touching inside only.


Mask - Break straps or remove by ears, placing mask directly into clinical bin without touching the outer layer.

Eye and face protection - Remove without touching outside surface. Dispose of single-use items into clinical waste.

Wash hands thoroughly again.



### PPE Removal NO VISOR G A M E E M



IPC Lead Module 3 Slides Page 9 of 12

### Surface decontamination and zoning

- Surfaces jointless as far as reasonably possible
- Cleaned before and after every patient
- Clean-to-dirty workflow
- Impervious flooring
- No carpets
- Cleaning code of practice




### Surface decontamination and zoning

### Between each patient the following should be cleaned:

- Work top
- Dental Chair
- Curing lamps
- Inspection lights and handles
- Hand controls
- Spittoons
- Aspirators
- X-ray units

Keyboards and mouse covers should be used in clinical areas.





IPC Lead Module 3 Slides Page 10 of 12


### **Zoning**

### Clean area above and below the work surfaces:

- hand washing sinks
- Stock
- PPE
- Clean instruments
- All clean draws with filling materials
- Impressions
- Local anaesthetics

Please be aware that due to aerosols as much as possible all PPE and consumables should be covered in draws





### Zoning

### A dirty area will contain:

- Setting down area for instruments
- Washing and rinsing sinks or bowls
- Ultrasonic bath, washer disinfector and inspection light
- Tooth box , sharps and amalgam waste
- Clinical waste bin



IPC Lead Module 3 Slides Page 11 of 12

Cleaning schedule
A surgery cleaning checklist should be used to show compliance with the HTM 01-05 and Code of practice.
The Dental Nurse Network have provided a checklist that you can download.
Summary
Hand hygiene
• PPE
Surface decontamination and Zoning
Surface decontainination and zoning

IPC Lead Module 3 Slides Page 12 of 12